Bangert-Software

INSTALLATION AND UPDATE

Musikregal for Windows

VMW-3.0.0-R1-ID70F · Windows x64 · 45-day trial

Up to four windows

Arrange the player, track list and display across screens according to your edition.

Direct music access

Play local files and music from NAS, network shares and OneDrive.

18 frequency bands

Keep the frequency display and output level in view.

A/B crossfade

Prepare the next track and mix it in with the crossfader in the applicable edition.

www.be-edvsysteme.de/software/vmw-downloads.html

software@b-termine.de

Release notes

Install and open the player

Close Musikregal and back up existing data first. Extract the matching installation ZIP and run Setup.exe. Fresh public and private installations use the same default folder C:\B-Software\Musikregal. An update uses the actual existing installation folder, even if different. Update over the existing installation; do not uninstall or delete data first. A compatible update preserves data, settings, valid licences and the original trial period. The desktop shortcut starts the player. Music files stay in place.

Language on installation and update

A fresh private installation starts in German without a language prompt. A fresh public installation first offers language selection, with a supported system language preselected and manually changeable. Order: German, English, Greek, Dutch, French, Spanish, Portuguese, Russian. German is the fallback for other system languages. Updates preserve the previously chosen language.

Connect optional OneDrive unambiguously

The OneDrive music source uses Musikregal directly at the root of personal OneDrive: OneDrive/Musikregal. Music may be in subfolders. Share that exact folder with read access, copy its link, enter it in VMW and choose Check connection. Verification confirms the actual root folder, identity and readable access; another folder is not a substitute. The adapter supports readable personal shares without additional sign-in. Integrated Microsoft sign-in/OAuth and business or sign-in-required shares are not configured. The fixed root rule applies to OneDrive, not local or NAS paths. After a successful check choose “Save verified connection”. The source is applied without restarting; a saved link stays hidden.

Switch sources independently and persistently

Every configured source has its own saved on/off state. Disabled sources are not used for new searches, preloading or playback and are not automatically enabled as fallback. Main and fallback sources must be configured, enabled and reachable. Switching off a source or losing the network deletes neither its files nor its saved catalogue.

Move the program folder to another PC

Close VMW completely and back up the existing program and data. Music paths and network shares must be reachable on the destination PC; confirm window positions there. Windows-protected sharing links are bound to the user and computer by DPAPI. A copied encrypted link cannot automatically be reused: deliberately relink the source and run Check connection. Files and collection are retained.

Track counts without duplicate mirrors

In Hartmut’s private edition, an enabled, fully confirmed OneDrive snapshot is the authoritative reference catalogue. Local mirrors are not counted again. Local-only tracks are then hidden in that edition, but remain saved. Switching OneDrive off makes local sources independently available again. In the public edition, additional local tracks remain visible even with OneDrive enabled; conclusively verified mirrors are still counted only once. Being offline or an incomplete scan does not delete data. Mirror matching checks path, size and real metadata; conflicting hashes prevent a match. Matching filenames alone justify neither a mirror match nor deletion.

Tracks and file locations

Excluded tracks in Music management shows tracks removed from the regular mix. Allow track again restores a track. Right-click or hold a title to check each file’s bitrate. Moving a writable OneDrive file to the recycle bin requires confirmation.

Track counter and EQ

A track is counted after 60 seconds of playback. The count continues when switching lists. Hold the counter for two seconds to reset it. EQ response changes the display speed in the player and the EQ window.

Choose your edition

Light offers the player and track list in up to two windows. Standard combines the player and track list and adds a separate EQ. Professional gives the player, EQ, library and queue up to four freely positioned windows.

Try it for 45 days

The public Demo45 starts in Professional. Use Try an edition to explore the three player views within a single trial. Music and the queue continue when you switch. Information and demo at b-termine.de.

Music directly from your sources

Local music remains independent and usable offline. Each source has a saved on/off choice. Optional OneDrive: fixed root folder Musikregal, individual readable sharing link and Check connection. NAS and PC/server shares must be reachable.

Set up the windows in order

Open and position the four windows in order. Confirm the player, EQ and music library to unlock each next window. Confirm the queue as well. At the next start, VMW restores the confirmed position, size and full-screen state for this display arrangement. Confirm again to save a change. Use F11 to enter full screen and Esc to leave it.

Player at a glance

The timeline sits above the transport controls, with a toggle for volume. Play, Pause and Stop use distinct colours. Search and filters stay at the top of the library. A Now playing label marks the active track. Radio starts collapsed outside the player. The timeline, playback buttons and A/B crossfader stay in place when the volume slider opens or closes.

Volume and output level

The meter beside Volume always stays visible. With the slider closed, it fills the available width. When open, the slider is on the left and the meter on the right, each using 50% of the width. In narrow windows, the slider occupies a reserved second row. The timeline, playback buttons and A/B crossfader stay in place. The percentage is centred beneath the slider and changes in half-percentage-point steps. Its field is green through 75%, orange at 75.5–90%, and red from 90.5%. The meter keeps measuring during playback in both states and holds its peak for half a second.

Blutfang in Musikregal

Look for the lamb and the small switch at the bottom right of the player. After you turn it on, Blutfang waits 5–10 seconds. A single click enables a random visit every two hours, and a double-click enables one per hour. He stays quiet while music plays. Press Esc to end a visit.

Player and library

The header shows the source used for playback. Use the adjacent button to hide or show it. In the separate library, search, filters and actions stay visible. Find years, sources and list options under View & collection. Two shades of green and the digits 1 and 2 show the favorite rating. Favorites stays on one line in a narrow queue window. The clearing hint and the actions have separate areas with spacing.

Preparing the next track

VMW can use complete recordings from its local cache immediately. Tracks outside the cache follow your source order. Optional loudness analysis runs in the background. VMW sets the gain at the start of the track and keeps it steady. Blutfang’s leap features a sharper close-up.

Track changes during preloading

Next track reuses the next track’s ongoing preparation. The player shows its loading state until it is ready. Crossfade now queues the transition and keeps the current track playing until the next one is ready, then starts the fade. Pause, Stop or another track jump cancels the queued transition.

Mix with the A/B crossfader

Green shows that the next track is ready. Drag the crossfader or click Crossfade now. The fader follows the transition in either direction. The next three tracks appear underneath.

Log a request in one click

Choose Request +1 beside a track to record a request. The ranking lists the most requested tracks.

Display and power

VMW temporarily inhibits the screensaver, automatic display sleep and idle standby while it is open. Windows resumes its configured behaviour when VMW exits.

Favorites and playlists across PCs

In Music management → Sources → OneDrive sync, choose the synced Musikregal folder on each PC. The music source must point to this folder or a subfolder. VMW reads Musikregal-Listen.json on startup and saves changes on exit or when you select Sync now. Wait for OneDrive to finish syncing before switching PCs. Playlists with tracks outside the shared folder stay on their PC. Read access to music does not replace read/write permissions for list synchronisation.

Update the library

Refresh library adds new files and removes paths confirmed no longer present. Removal is allowed only after a fully successful scan of the relevant enabled, reachable source. Cancellation, read errors, missing permission, partial scans and disabled or unreachable sources do not delete their entries. Preview and Apply changes cover manual reconciliation; automatic scans use the same safeguards. A track is removed from the library when its last confirmed location is missing. Original MP3 files are unchanged.

Checks and release status

Build and test reports demonstrate only the checks actually recorded. Audio playback, multiple physical monitors, Windows installation, restore and real NAS/OneDrive connections require checks on the intended Windows PC. These documents do not claim completed Windows device acceptance or live network testing.

Laptop sources and music index

Private edition: At home is the default under Music management → Sources. VMW uses M:\Musikregal first and N:\Musikregal as the backup. Enable Travelling if the laptop may use your configured OneDrive when both NAS folders are unreachable. A partial cloud inventory leaves NAS entries intact. Import music index accepts CSV, result ZIP and JSONL.GZ. Refresh checks additions and missing files on reachable sources. Track details show artwork and labelled language clues where available.